


Protect your investments with Protection!

---



---

# Protection!™

Licensing Server

v4.9

**Administrator Guide**

---

**Notice of Copyright**

Published by jProductivity, LLC

Copyright ©2003-2018

All rights reserved.

**Registered Trademarks and Proprietary Names**

Product names mentioned in this document may be trademarks or registered trademarks of jProductivity, LLC or other hardware, software, or service providers and are used herein for identification purposes only.

**Applicability**

This document applies to Protection! Licensing Server v4.9 software.

# Contents

---

Contents .....	3
1. Protection! Licensing Server Overview .....	4
1.1 Protection! Licensing Server .....	4
1.2 Protection! Licensing Server Management Console .....	4
2. Working with the Protection! Licensing Server .....	6
2.1 Configuring the Licensing Server .....	6
2.2 Running the Licensing Server .....	7
2.2.1 Microsoft Windows.....	7
2.2.2 Unix .....	8
2.3 Shutting Down the Licensing Server .....	8
2.4 Analyzing the Licensing Server Logs .....	8
2.5 Automatic Reloading of Configuration Files .....	9
3. Working with the Licensing Server Management Console .....	10
3.1 Connecting to the Licensing Server(s).....	10
3.2 Summary Screen .....	11
3.2.1 Connection Dashboard .....	11
3.2.2 Licensing Statistics Dashboard .....	12
3.2.3 Server Control Dashboard .....	12
Shutting Down the Licensing Server.....	12
Disabling/Enabling Licensing Activities.....	13
3.2.4 Server Summary Dashboard .....	15
3.3 License Storage Screen.....	15
3.3.1 Maintaining License Storage .....	15
3.3.2 Maintaining LDAP Connection.....	16
3.3.3 Maintaining License Users and License User Groups .....	17
Maintaining License Users.....	17
Maintaining License User Groups .....	18
3.3.4 Allocation of Licenses for Specific Users and/or User Groups .....	21
3.4 License Sessions Screen .....	23
3.4.1 Monitoring License Sessions.....	23
3.4.2 Revoking License Sessions .....	24
3.5 Managing Licensing Server Users .....	25
3.6 Maintaining Access Control List .....	26
Feedback.....	29

---

## Protection! Licensing Server Overview

Protection! Licensing Server consists of two major components to support the Licensing Server functionality – the Licensing Server itself and the Management Console.

### 1.1 Protection! Licensing Server

---

Licensing Server is responsible for:

- Distribution of licenses so a client application may ask Licensing Server to obtain (download) desired license for a certain user. To achieve it - licenses to distribute must be added to the Licensing Server and allocated to the particular users or groups. See [Allocation of Licenses for Specific Users and/or User Groups](#) for more information.
- Tracking of the concurrent use of licenses to support Floating and Named licensing models. Those models assume that only a certain number of users can work concurrently with the license according to the license number of copies value. Actual usage check is done by contacting the Licensing Server and acquiring the License Lock. After the application quits - it must release License Lock to free that license and make it available for other users.

Note

There are almost completely independent sub-systems for licenses distribution and for concurrent models support. Therefore:

- a) Licenses of any type and any user licensing model can be distributed by the Licensing Server.
- b) Licensing Server allows tracking of concurrent use of the licenses regardless how those licenses were obtained.

The Licensing Server application is a turnkey solution that is deployed inside the customer's network. It can be run as a Windows service or as a UNIX/Linux daemon. The main features of the Licensing Server are:

- Support for Floating and Named User models by tracking licenses usage using the concept of license lock (acquire) and unlock (release).
- Ability to revoke license locks sessions to force client applications to unlock (release) licenses.
- License lock session's expiration to allow correctly releasing of the license lock when the client application is not responding or the network (connection to the Licensing Server) is down.
- Ability to host and to distribute an unlimited number of licenses for an unlimited number of products.
- Ability to allocate licenses for specified users and/or user groups.
- Ability to control access to the Licensing Server by using access control lists (whitelist and blacklist) for any types of operations.
- Ability to remotely monitor and manage the Licensing Server via supplied Management Console application.

### 1.2 Protection! Licensing Server Management Console

---

The Management Console is a GUI application intended for remote monitoring and management the Licensing Server(s). The main features of the Management Console are:

- Authentication and authorization per Licensing Server with the ability to maintain the Licensing Server users.
- Support for multiple Licensing Server connections.
- Ability to discover running instances of the Licensing Servers via network broadcast.
- Ability to maintain access control lists.
- Ability to view licensing statistics and server statistics.
- Ability to disable/enable any licensing activities.
- Ability to shut down the Licensing Server.
- Ability to visually monitor current license sessions.
- Ability to revoke specific license sessions.
- Ability to maintain licenses storage.
- Ability to maintain license users/groups
- Ability to allocate licenses for specified users and/or user groups.
- Ability to allocate licenses to the users fetched fro LDAP directory




Figure 1: Licensing Server Management Console

## Working with the Protection! Licensing Server

This topic outlines how to work with the Licensing Server application running on the different platforms.

### 2.1 Configuring the Licensing Server

The Licensing Server configuration can be done by modifying the `bin/server.xml` file. The following attributes of the `<server>` element can be specified:

- *hostName* - represents the fully qualified host name or public IP address of the physical server the Licensing Server is running on. The *hostName* attribute must be explicitly specified when the server is running behind the firewall. Default value is "" which means that local IP of the server will be used.
- *port* - the port that is used by the Licensing Server to accept requests from the clients. Default value for the *port* attribute is 1099. If a different value is specified for the *port* attribute then it must be explicitly specified for all of the Licensing Server connections.
- *exportPort* - represents the port number that is used by the Licensing Server to receive calls from the clients. Default value for this attribute is 0 which means that the server's listening port is chosen arbitrarily at runtime. The *exportPort* attribute must be explicitly specified when the server is running behind the firewall.
- *mgmtPort* - the port that is used by the Licensing Server to accept requests from the Management Console to allow remote management of the Licensing Server. Default value for the *mgmtPort* attribute is 9999. If a different value is specified for the *mgmtPort* attribute then it must be explicitly specified for all of the Management Console connections.
- *mgmtExportPort* - represents the port number that is used by the Licensing Server to receive calls from the Management Console. Default value for this attribute is 0 which means that the server's listening port is chosen arbitrarily at runtime. The *mgmtExportPort* attribute must be explicitly specified when the server is running behind the firewall.

Example of the `<server>` element would be as following:

```
<server hostName="" port="1099" exportPort="10991" mgmtPort="9999" mgmtExportPort="9998" allowRestart="false">
```

Note

The *hostName*, *exportPort* and *mgmtExportPort* attributes must be explicitly specified when the server is running behind the firewall.

Note

The *port*, *exportPort*, *mgmtPort* and *mgmtExportPort* ports must be opened in the firewall configuration when the server is running behind the firewall but must be accessed from outside of the firewall.

Note

The Licensing Server must be restarted to apply changes in the configuration.

If you experience any issues during functioning of the Licensing Server - turn on DEBUG logging to see some more detailed info.

## 2.2 Running the Licensing Server

The Licensing Server application is a turnkey solution that is deployed inside the customer's network. It can be run as a Windows service or as a UNIX/Linux daemon. Licensing Server can also be started as an application via the command line:

```
java -jar ProtectionLS.jar
```

The following screenshot illustrates sample output when Licensing Server has been started via command line:



```
C:\src\ProtectionLS\bin>java -jar ProtectionLS.jar
Protection! 3.0 RC2 Licensing Server. Copyright (c) 2003-2007 jProductivity, LLC
2007-04-14 21:35:07,234 INFO [main] - STARTING
2007-04-14 21:35:07,234 INFO [main] - STARTING licenseSessionManager
2007-04-14 21:35:07,250 INFO [main] - STARTED licenseSessionManager
2007-04-14 21:35:07,250 INFO [main] - STARTING serverSessionManager
2007-04-14 21:35:07,250 INFO [main] - STARTED serverSessionManager
2007-04-14 21:35:07,250 INFO [main] - STARTING rules
2007-04-14 21:35:07,281 INFO [main] - STARTED rules
2007-04-14 21:35:07,281 INFO [main] - STARTING licenseSessionStorage
2007-04-14 21:35:07,281 INFO [main] - STARTED licenseSessionStorage
2007-04-14 21:35:07,281 INFO [main] - STARTING authenticator
2007-04-14 21:35:07,546 INFO [main] - STARTED authenticator
2007-04-14 21:35:07,546 INFO [main] - STARTING networkDiscovery
2007-04-14 21:35:07,562 INFO [main] - STARTED networkDiscovery
2007-04-14 21:35:07,562 INFO [main] - STARTING licenseStorage
2007-04-14 21:35:07,593 INFO [main] - STARTED licenseStorage
2007-04-14 21:35:07,593 INFO [main] - STARTING launcherStorage
2007-04-14 21:35:07,625 INFO [main] - STARTED launcherStorage
2007-04-14 21:35:07,625 INFO [main] - STARTING licenseUsers
2007-04-14 21:35:07,640 INFO [main] - STARTED licenseUsers
2007-04-14 21:35:07,640 INFO [main] - STARTING managementSupport
2007-04-14 21:35:07,781 INFO [main] - STARTED managementSupport
2007-04-14 21:35:08,093 WARN [main] - This server MUST NOT be used for commercial deployments!
2007-04-14 21:35:08,093 INFO [main] - STARTED
2007-04-14 21:35:08,109 INFO [main] - BOUND: rmi://localhost:1099/LicensingServer
Type Ctrl+C to exit.
```

Figure 2: Starting the Licensing Server via command line

### 2.2.1 Microsoft Windows

The Licensing Server Windows service is registered by the Licensing Server installer. It is also possible to install services from the command line by passing `/install` to the `ProtectionLS.exe` service executable. If the Licensing Server service is installed via command line then the default start mode of the service can be determined as follows:

- Start on demand - In start on demand mode, the Licensing Server service must be manually started by the user in the Windows service manager. This start-up mode can be forced on the command line if the user passes `/install-demand` to the Licensing Server executable instead of `/install`.
- Auto start - In auto start mode, the Licensing Server service is always started when Windows is booted. This installation mode can be forced on the command line if the user passes `/install-auto` to the Licensing Server executable instead of `/install`.
- Windows services are always uninstalled by passing `/uninstall` to the Licensing Server service executable. All command line switches also work with a prefixed dash instead of a slash (like `-uninstall`) or two prefixed dashes (like `--uninstall`).

To start or stop the Licensing Server service, the `/start` and `/stop` options are available respectively. In addition, a `/status` argument shows if the service is already running. The exit code of the status command is 0 when the Licensing Server service is running, 3 when it is not running and 1 when the state cannot be determined (for example when it is not installed on Windows).

As a second parameter after the `/install` parameter, you can optionally pass a service name. In that way you can install the Licensing Server service with a different service name than the default name. Protection! Licensing Server will allow only a single running service instance regardless if multiple services with different names were installed. You will not be able to use the same Licensing Server service executable to start multiple services with different names.

Note

If you install Licensing Server service with a different name than its default name then you also have to pass the same service name as the second parameter if you use the `/uninstall`, `/start` and `/stop` parameters.

### 2.2.2 Unix

For Unix service executables, the `start`, `stop` and `status` arguments are available for the Licensing Server start script (by default script is called `ProtectionLS` and it is located in the `/bin` directory). The `stop` command waits for the Licensing Server service to shut down. The exit code of the status command is 0 when the Licensing Server service is running and 3 when it is not running.

On Unix-like platforms, the Licensing Server start/stop script has to be integrated into the boot sequence by the administrator.

## 2.3 Shutting Down the Licensing Server

---

To shutdown the Licensing Server:

- If the Licensing Server is running as a Windows service or as a UNIX/Linux daemon - use an appropriate OS command to stop the service/daemon or by passing `/stop` to the Licensing Server service executable.
- If the Licensing Server started as an application via the command line then to shut down the server send an appropriate interrupt command (e.g., `Ctrl+C`).
- You can also stop the Licensing Server service via the Licensing Server Management Console. In the Management Console click on Summary shortcut on the Shortcuts Side Bar and in the Server Control panel click the "Shutdown" button (see the topic "*Shutting Down the Licensing Server via Management Console*" later in this Guide).

## 2.4 Analyzing the Licensing Server Logs

---

All of the Licensing Server activities are written into the log files located in the `<Licensing_Server_Install_Folder>/logs` folder. The logs are rolled over daily by default where the older (rolled over) logs are automatically renamed using the following naming convention `<log_name.log.yyyy-mm-dd>`.

There are 2 (two) server logs – `access.log` and `error.log`. Access log contain all of the Licensing Server start/stop events, all licensing activities and errors (e.g., when a port is occupied by a different service). Error log just contains all of the Licensing Server errors.



It is possible to configure and fine tune the Licensing Server logging sub-system by modifying the `<Licensing_Server_Install_Folder>/conf/log4j.properties` file. Please consult the log4j documentation (<http://logging.apache.org/log4j/docs/>) for more information.

## 2.5 Automatic Reloading of Configuration Files

---

To allow bulk modification of configuration files the Licensing Server provides automatic reloading of them. This can be useful, for example, to import all the users from the corporate directory.

To prevent concurrent modification and possible data corruption you must first create an empty lock file. Such lock file should be named as a file to alter, adding `.lck` extension. Certainly, any lock files must be removed after complete of update.

For example, to update license users file (`licenseUsers.xml`): a `licenseUsers.xml.lck` file must be created; then license users file should be updated and finally the lock file should be removed.

Note

File locks may be automatically cleared (removed) after 1 min of timeout. This is done to avoid orphaned file locks that would prevent any further configuration updates done even using the Management Console. So any updates should be done within 1 min time range.

The following files in the `<Licensing_Server_Install_Folder>/conf/` can be updated on the fly:

- `acl_named.xml` - ACL | Lock License-Named
- `acl_floating.xml` - ACL | Lock License-Floating
- `acl_get.xml` - ACL | Obtain License
- `acl_global.xml` - ACL | Global
- `licenseUsers.xml` - License Users. Note: when defying LDAP Connection attributes the password must be specified either as an unencrypted value or an encrypted value copied from `licenseUsers.xml` previously generated by Licensing Server itself.

## Working with the Licensing Server Management Console


This topic outlines how to use the Licensing Server Management Console to manage Licensing Servers.

### 3.1 Connecting to the Licensing Server(s)

The Licensing Server Management Console allows the administrator to connect to multiple running instances of the Licensing Server(s). If there is no connections setup then "New Connection" dialog would be launched automatically on the first run of the Licensing Server Management Console.

To set up a new connection the following steps needs to be performed:

1. Click the "New Connection" button on the Management Console toolbar or by selecting the *File|New Connection* menu item.
2. In the New/Edit Connection Dialog shown on the screen enter the following attributes:
  - a. Name – Unique name for connection. This name will be shown in the connections drop-down on the Management Console toolbar;
  - b. Description – detailed description of the connection;
  - c. Host – specifies hostname or IP address of the Licensing Server;
  - d. Port – specifies port of the Licensing Server;
  - e. Login and Password required for authentication.



**Figure 3: New Connection dialog**

3. Press the OK button to close the dialog and to create a new connection.


For the fresh install, you can use one of the predefined users to specify login information (leave password blank):

- a. **admin** – administrator with full access permissions.
- b. **manager** – manager with full access permissions except ability to manage Licensing Server users.
- c. **user** – with read-only access permissions.

When a new connection is created it will be shown in the Summary Screen | Connection dashboard outlining connection parameters.

Appropriate buttons on the application toolbar or in the Summary Screen | Connection dashboard allows the following actions:

1. Connect – connects to the specified Licensing Server;
2. Edit – Launches “Edit Connection” dialog for connection parameters modification;
3. Delete – Deletes selected connection.



**Figure 4: Connection Summary**

It is possible to change the current connection using the connections drop-down on the application toolbar or via the *View | Connection* menu.

## 3.2 Summary Screen

This screen provides the ability to view Connection information, Licensing Statistics and the Licensing Server summary and to perform certain actions via the set of dashboards.

To activate the Summary screen select the Summary  icon on Shortcuts Side Bar or use the *View | Summary* menu item.

### 3.2.1 Connection Dashboard

This dashboard provides the summary for selection connection and provides the following actions via corresponding buttons:

1. Connect – connects to the specified Licensing Server;
2. Edit – Launches “Edit Connection” dialog for connection parameters modification;
3. Delete – Deletes the selected connection.

### **3.2.2 Licensing Statistics Dashboard**

This dashboard provides the ability to view licensing statistics for the selected scope (e.g. for today, overall or several days ago).

The *Scope* combo box allows choosing the desired scope to view.

The requests statistics shows:

- a. *Succeeded* – number of succeeded requests;
- b. *Failed* – number of failed requests;
- c. *Errors* – number of errors that occurred during requests processing.

The active session’s statistics shows:

- a. *Current* – number of active license sessions;
- b. *Max* – maximum number of active license sessions.

It is possible to download detailed statistics reports for a selected scope using the *Download Reports* button. The following reports are available:

1. *Usage per User* –license utilization per user over time.
2. *Total Users (Succeeded)* - total number of users utilizing licenses within a timeframe.
3. *Total Users (Failed)* - total number of users failed to utilize licenses within a timeframe.
4. *Statistics* – report for all licensing activities.

Most of columns in those reports are self-explained. Some columns may need more explanation:


1. *Operation* – shows operation performed by Licensing Server. Possible values are:
  - a. *LOCK* – license lock was obtained (aka. checked-out).
  - b. *UNLOCK* – license lock was released (aka. checked-in).
  - c. *OBTAIN* – license was obtained (aka. downloaded).
2. *Result* – result of the operation. Possible values and corresponding codes are:
  - a. *OK = 1* – operation was successful.
  - b. *Error = 2* – operation was failed
  - c. *System Error = 3* – operation was failed with unexpected system error
  - d. *Expired = 5* – license session was expired because a client application was terminated or a computer just went to sleep.
  - e. *Access Denied = -1* – operation was failed because access was denied by administrator rule.

### **3.2.3 Server Control Dashboard**

This dashboard optionally shows information about the status of the Licensing Server in the yellow message box on the top and provides the ability to shut down the Licensing Server and to disable/enable licensing activities.

#### **Shutting Down the Licensing Server**

The Shutdown button allows to remotely shutdown the Licensing Server. After clicking the Shutdown button the current connection will be closed and the Licensing Server shutdown will be initiated.




**Figure 5: Shutting Down the Licensing Server Instance**

Note

Current implementation has no ability to start/re-start the Licensing Server after the shutdown process has been initiated.


### Disabling/Enabling Licensing Activities

In some cases the Administrator needs to temporarily disable all licensing activities without shutting down the Licensing Server. This is especially useful if the Licensing Server maintenance needs to be performed such as user and user group's management, access control list management, etc. The Disable button allows disabling all licensing activities.




**Figure 6: Disable all licensing activities**

After pressing the Disable button the confirmation dialog will be shown on the screen providing optional reason why all licensing activities will be disabled.




**Figure 7: Confirmation dialog with optional reason**

Any new license lock requests from the clients would not be fulfilled while the Licensing Server in the disabled state. Any client application trying to acquire license lock from the licensing server will see the following dialogs:



**Figure 8: License Lock assistant – unable to acquire lock**



**Figure 9: Client application message**

Note

The disabled state of the Licensing Server is not persisted and will be cleared during the Licensing Server re-start.

When Licensing Server is in the disabled state the Enable button allows restoring licensing activities. After clicking the Enable button all licensing activities will be immediately enabled.





Figure 10: enable all licensing activities

### 3.2.4 Server Summary Dashboard

This dashboard shows information about resources used by the Licensing Server. This information includes:

1. Up time;
2. CPU usage;
3. Threads statistics;
4. Memory statistics;

## 3.3 License Storage Screen

The License Storage screen provides the ability to maintain licenses available for distribution and to allocate them to the users. To activate the screen select the License Storage  icon on Shortcuts Side Bar or use the *View | License Storage* menu item.

### 3.3.1 Maintaining License Storage

The Licensing Server Management Console provides the ability to maintain the License Storage. License Storage is designed to store products and their licenses in one uniform location (container) and optionally allocate license users and/or license user groups with appropriate licenses. The License Storage allows holding and storing an unlimited number of products and their licenses.

Note

Products must first be imported into the License Storage before the licenses for these products could be imported.

To import products:

1. Choose the *File | Import Product* menu item;

2. Navigate to the supplied by vendor product file (e.g. `DemoCalc.product`) and select it;
3. Press OK to import selected product.

Tip

Product (e.g. `DemoCalc.product`) is actually a Launcher for corresponding product. To get it - build a Launcher file (using Protection! Developer Control Center or Protection! Builder Utility) for a Launcher Builder Configuration with Encryption turned OFF.

To view imported products and their versions use the Products dialog that can be shown using the *View | Products* menu item.

To import licenses:

1. Choose the *File | Import Licenses* menu item;
2. Navigate to supplied by vendor license(s) and select it ('em);
3. Press OK to import selected license(s).

Details for selected license could be seen on the License Tab at the right of the screen.





Figure 11: License Storage Screen – License Information

### 3.3.2 Maintaining LDAP Connection

To allow allocation of licenses to the users fetched from a LDAP directory – the LDAP Connection should be specified via the *"Edit | LDAP Connection"*.





**Figure 12: LDAP Connection Dialog**

There the following connection attributes can be specified:


1. URL – an URL to a directory server that supports LDAP protocol. The URL must have ldap scheme e.g. ldap://sample.com:389. If port is not explicitly specified – port 389 will be used by default.
2. Bind DN or User – bind DN or user name to authenticate the connection. Note: only BASIC authentication is currently supported.
3. Password – password.

### **3.3.3 Maintaining License Users and License User Groups**

The Licensing Server Management Console provides the ability to maintain list of license users and license user groups that could be associated with the licenses in the License Storage.

#### **Maintaining License Users**

1. Click the *Edit | License Users* menu item;
2. The License Users dialog will be shown on the screen displaying the list of available license users;



**Figure 13: License Users Dialog**

3. Choose the appropriate option from the License Users Dialog:
  - a. New – to create new user;
  - b. Edit – to modify parameters for selected user;
  - c. Delete – to delete selected user.

There are several attributes that could be specified for the license user:

1. Name – specifies user descriptive name;
2. User Name – specifies user's system name. In general this would be the same name (sometimes referred to as "User Id") that is used by the user as identification and is required when logging on to a computer system;
3. Host – specifies user's computer name;
4. IP address – specifies user's private IP address. IP addresses are written in "dotted decimal" notation, which is four sets of numbers separated by periods; for example, 192.168.1.1. Currently only the traditional IP address (IPv4) is supported;
5. Member Of Tab – provides ability to associate the user with the License User Group.




The image shows a screenshot of a software dialog box titled "Add User". The dialog has a title bar with a close button (X) on the right. Below the title bar are two tabs: "General" and "Member Of". The "General" tab is selected. Inside the dialog, there are four input fields: "Name" containing "John Doe", "User Name" containing "john.doe", "Host" which is empty, and "IP Address" containing three dots. At the bottom of the dialog are three buttons: "OK", "Cancel", and "Help".

**Figure 14: Add User Dialog**

### **Maintaining License User Groups**

To maintain License User Groups - Choose *Edit | License User Groups* menu item. The License User Groups dialog will be shown on the screen displaying the list of available license user groups.



**Figure 15: License User Groups Dialog**

There it is possible to make the following actions:


- a. New – to create new group
- b. Edit – to modify parameters for selected group
- c. Delete – to delete selected group

There are several pages of attributes that could be specified for the license user group:

### **General**

The following attributes can be specified on the General page:

1. Name – specifies user group descriptive name;
2. Host – specifies range of user's computer names virtually belonging to the group; Usual \* and ? wildcards can be used there. For example, specifying the \* as host name allows defining the user group that virtually contains all users from any hosts;
3. IP address – specifies range of private IP address of users virtually belonging to the group. IP addresses are written in "dotted decimal" notation, which is four sets of numbers separated by periods; for example, 192.168.1.1. Currently only the traditional IP address (IPv4) is supported. Usual \* and ? wildcards can be used there;



**Figure 16: Add License User Group | General**

### **Members**

The Members page provides the ability to associate users with the License User Group. There it is possible to add the users to the group or delete them.




**Figure 17: Add License User Group | Members Page**

## LDAP Members

The LDAP Members page provides the ability to associate the users fetched from a LDAP directory with the License User Group. Note: to make this working – LDAP Connection must be configured first (Edit | LDAP Connection).

The following attributes can be specified in the LDAP Members page:

1. DN and Filter properties to point to desired set of users. Test if those users are correctly fetched by pressing the Test button.
2. "Property Mapping" to define how to map the User Name (login), Host and IP address to corresponding fields in LDAP objects. At least one mapping must be specified.





**Figure 18: Add License User Group | LDAP Members Page**

### 3.3.4 Allocation of Licenses for Specific Users and/or User Groups


The Licensing Server Management Console provides the ability to allocate license users and license user groups to the licenses in the License Storage that allows defining which license(s) are available to which users.


To associate a license user and/or license user group with the license:

1. Select a specific license in the License Entries Grid;
2. Click the Add User button ;
3. Select appropriate license user(s) and/or license user group(s) from the Add Users / Groups dialog. Multiple selections could be done by either holding a *Control* or a *Shift* keyboard key.




**Figure 19: Associate License Users / Groups with the license**

To remove the association between the license users/groups and the license select desired users/groups and press the  button.



**Figure 20: License User and User Group Allocation**

### 3.4 License Sessions Screen

The Licensing Server Management Console provides the ability to visually monitor all currently running license sessions. To activate the screen select the License Sessions  icon on Shortcuts Side Bar or use the *View | License Sessions* menu item.

#### 3.4.1 Monitoring License Sessions

The License Sessions Grid shows all the currently running License Sessions. It is possible to view details for a selected License Session using the Details Pane.




Figure 21: License Sessions Screen


### 3.4.2 Revoking License Sessions

The Licensing Server Management Console provides the ability to revoke any of the currently running license sessions.


Note

If the License Session to be revoked is in use – the actual revocation will be replaced by a corresponding revocation request. If revocation request was placed then the corresponding License Session will continue to run until request is handled by the client application. It is up to client application implementation how to handle such requests. They could be accepted (leading actual revocation) or simply ignored e.g. based on the users' input.

To revoke license sessions:


1. Navigate to the desired license session in the License Sessions Grid;
2. Click Delete Icon  on the Management Console toolbar
3. In the confirmation dialog provide optional reason why specific license session needs to be revoked.





**Figure 22: Revoke License Session Confirmation Dialog**

The client application for which the license session has been revoked would receive the following notification:



**Figure 23: License Sessions Screen**

### 3.5 Managing Licensing Server Users


---

The Licensing Server Management Console provides the ability to manage Licensing Server system users. Only users with administrative privileges are able to maintain Licensing Server users. There are 3 (three) type of server users:

- *Administrator* – Has full Licensing Server and Management Console permissions;
- *Manager* – Same permission as *Administrator* user but can not manage Licensing Server Users;
- *User* – Can only view (read-only) Server activity and License Storage contents. Users with the *User* privileges can not disable Licensing Server licensing activities nor do they can shutdown the Licensing Server.

To maintain server users:

1. Choose the *Edit | Server Users* menu item
2. Choose appropriate option from the License Users Dialog:
  - a. New – to create a new user;
  - b. Edit – to modify parameters for the selected user;
  - c. Delete – to delete the selected user.



**Figure 24: Manage Server Users Dialog**

There are several attributes that need to be specified for the Server user:

1. Name – specifies user login name;
2. Password – specifies user’s password;
3. Confirm Password – confirms specified user’s password;
4. Role – specifies user’s role.



**Figure 25: Manage Server Users Dialog**

### 3.6 Maintaining Access Control List

Protection! Licensing Server provides functionality of the Access Control List (ACL) through the common concept of the white and black lists. An access control list is an access matrix, containing the access rights of various users, systems, etc to the Licensing Server processes. Licensing Server’s white list is a list of users, systems, etc that the Licensing Server is configured to accept. All licensing activities from the entries in the white list are allowed. White list is a contrast with the blacklist where given users, systems, etc are considered off limits and no licensing activities are allowed to any entry in the blacklist.


Licensing Server Management Consol provides administrator with the ability to maintain several different access control lists:

1. *Global* – an access control list that is applicable to any licensing activity;

2. *Lock License - Named User* - an access control list that is applicable only to licensing activities that are associated with the requests to obtain license lock for the licenses with the Named User Licensing models only;
3. *Lock License - Floating User* - an access control list that is applicable only to licensing activities that are associated with the requests to obtain license lock for the licenses with the Floating User Licensing models only;
4. *Obtain License* - an access control list that is applicable only to licensing activities that are associated with the requests to obtain a license from the Licensing Server.

Each of the above access control lists has its respective white lists and black lists. To maintain either white list or black list:


1. Choose desired ACL using the *Edit | Access Control List* menu;
2. Choose the *White List Conditions* or *Black List Conditions* menu item;
3. In the "Conditions" dialog create either new condition or new complex condition. Complex conditions allow using Boolean AND/OR logic to build hierarchical condition tree.




**Figure 26: White List Conditions dialog**

The New Condition dialog provides the following parameters to create condition:

1. Field – supports the following parameters:
  - a. Host
  - b. User Name
  - c. Private IP Address
  - d. Public IP Address
  - e. MAC Address
  - f. MAC Addresses
  - g. Install ID
  - h. Available Processors
2. Operation – supports the following parameters:
  - a. Equals
  - b. Not Equals
  - c. Has Value
  - d. Has No Value
  - e. In List
  - f. Not In List
  - g. Like
  - h. Not Like
  - i. Starts With
  - j. Not Starts With
3. Value – specifies value or a list of values that will be checked.



**Figure 27: New Conditions Dialog**



**Figure 28: New Complex Conditions Dialog**

## Feedback

---

As part of the continuing effort to improve our product, we welcome your comments, suggestions and general feedback regarding the product.

If you have questions about Protection!, please feel free to contact us for further information at [protection@jproductivity.com](mailto:protection@jproductivity.com), or visit our site at: <http://www.jproductivity.com>.

If you discover any issues or defects in Protection! - please send the description of them to [protection@jproductivity.com](mailto:protection@jproductivity.com).